


Finding Your Computers IP and MAC address

Windows PCs

1. Open the Windows Command window by selecting the Start Menu and typing 'cmd'. With Windows 8 and 10 you can use the Search Windows function to locate and open the Command window.
2. This should open the below window,
3. Type the following command and press enter to display your IP Address,
 - a. ipconfig /all



```

C:\Windows\system32\cmd.exe
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No
DNS Suffix Search List. . . . . : lib.strath.ac.uk
                                   strath.ac.uk


Ethernet adapter Local Area Connection:

   Connection-specific DNS Suffix  . : strath.ac.uk
   Description . . . . .           : Intel(R) Ethernet Connection I217-LM
   Physical Address. . . . .       : 98-90-96-C9-7F-F8
   DHCP Enabled. . . . .           : Yes
   Autoconfiguration Enabled . . . : Yes
   IPv4 Address. . . . .            : 130.159.82.53(Preferred)
   Subnet Mask . . . . .           : 255.255.255.0
   Lease Obtained. . . . .         : 27 October 2015 10:39:45
   Lease Expires . . . . .         : 01 November 2015 11:39:36
   Default Gateway . . . . .       : 130.159.82.100
   DHCP Server . . . . .           : 130.159.248.62
   DNS Servers . . . . .           : 130.159.248.50
                                   130.159.228.50
   Primary WINS Server . . . . .   : 130.159.18.25
   Secondary WINS Server . . . . . : 130.159.19.238
   NetBIOS over Tcpiip. . . . .    : Enabled

C:\Users\ras09101>
  
```

- b. Your IP address should be displayed adjacent to IPv4 Address. In this example the IP address is 130.159.82.53. Please note that the above example is showing the IP address for the Ethernet adaptor. If you are connecting via your wireless card then your IP address will be displayed under the Wireless adaptor list. You find this by scrolling through the information displayed after entering the above command.

4. Type the following command and press enter to display your MAC Address
 - a. getmac



```
C:\Windows\system32\cmd.exe
Microsoft Windows [Version 6.1.7601]
Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Users\ras09101>getmac

Physical Address      Transport Name
=====
98-90-96-C9-7F-F8    \Device\NPF{0C61EA1B-D09C-4665-BCED-BF62AB25B7D3}

C:\Users\ras09101>
```

- b. Your MAC address should display as above under Physical Address. In this example the MAC address is 98-90-96-C9-7F-F8

CONTACT US

Email: help@strath.ac.uk **Call:** 0141 548 4444

the place of useful learning

www.strath.ac.uk

University of Strathclyde Glasgow G1 1XQ

The University of Strathclyde is a charitable body,
registered in Scotland, with registration number SC015263

YOUR
INFORMATION
SERVICES
YOUR
RESOURCES...